



Moby Dick

P-00021


Good Deeds LLC Certificate of Analysis

12/31/20 harvest date

total cannabinoids 32.4% CBD 0.06% THC 30.04% decarb total .05% 26.4%

1A4080100000A8D000000898

This Product Has Been Tested and Meets the Quality Assurance Requirements of the State of Montana



https://portal.a2la.org/scopepdf/4961-01.pdf

Sample Handling

test ID B0MTZ sample date 1/5/21 2:48 PM order 9401 labID 1AC44 weight 1.1 g source 1A4080100000A8D000000892

Table with 3 columns: Method, equipment, and values for various tests like weights, potency, terpenes, pesticides, etc.

flower


moisture 6.63%

PASS

stems >3mm dia 0.00%

seeds 0.00%

PASS



bud



Potency

Table listing potency components like tetrahydrocannabinolic acid (THCa), delta-9-tetrahydrocannabinol, etc., with their percentages and estimated errors.

Terpenes

Table listing various terpenes such as beta-myrcene, alpha-pinene, linalool, etc., with their percentages and estimated errors.

Solvents

solvents not tested / not required

Pesticides (MT)

Table listing various pesticides like abamectin, acequinocyl, bifenthrin, etc., with their concentrations and limits.

Pesticides (other)

Toxic Metals

metals not tested / not required

Microbial

Table listing microbial tests for E. coli, Salmonella sp., molds, Aflatoxin, and Ochratoxin with their respective limits.

Comments

CBGa = 1.96%

Certified by:

Signature of Kyle Larson

Kyle Larson, MSc (Biology) Deputy Director 6073 US93N, Olney MT 59927 406-881-2019 rdb@stlmlabs.com

Printed 1/8/2021 10:31 AM

All testing was completed onsite at 6073 US93N, Olney MT. Potency (cannabinoid concentration) is calculated from the equation: [cannabinoid] = [cannabinoid]HPLC x volume_dilution / m_dry. Terpene concentration is calculated from the equation: [terpene] = (terpene mass)GCMS / m_dry. Decarboxyted cannabinoid concentration is calculated from the equation XXX_total = 0.877 x XXXa + XXX. Standards are used to calibrate the resulting data and estimate error using a standard estimate of error method; this is combined with error from weighing and dilution using the propagation of error formula Sg^2 = sum (df/di)^2 * Si^2 where i is the contributor to error. The 95% confidence range is calculated from the equation: (concentration) +/- tCL90 * X Sg. Sampling error is not